

## Sentinel Run-time Environment (R[.])

07/16/2020 19:06:35

[FAQ Article Print](#)

<b>Category:</b>	FAQ in English::KOMPAS-3D Home	<b>Last update:</b>	12/19/2013 10:51:07
<b>State:</b>	public (all)		

### Keywords

rte, install, driver

### Problem (public)

How should I install/reinstall Sentinel Run-time Environment (RTE)?

### Solution (public)

NOTE! Before installation, please, do the following:  
close all HASP-protected applications disconnect all usb-keys HASP (not only one used for ASCON Software) disable UAC, antivirus and firewall if enabled (or ask your system administrator to do it)

To install/reinstall Sentinel RTE haspdinst.exe file is required.

You can find it in <KOMPAS-3D V13 Home Installation Path>/HASP/ directory (C:/Program Files/ASCON/KOMPAS-3D V13 Home/HASP/ or C:/Program Files (x86)/ASCON/KOMPAS-3D V13 Home/HASP/ by default).

NOTE! If you face any problem with Sentinel RTE installation, please, download actual Sentinel RTE version [1]here and then unpack it.

To install/reinstall Sentinel RTE automatically HASP\_install.cmd file is needed.

If you have downloaded actual RTE version, you can find this file in the downloaded archive.

In other case, please, download this file [2]here and unpack it into the directory which contains haspdinst.exe file.

To launch HASP\_install.cmd in Windows XP just make double click on it.  
To launch HASP\_install.cmd in Windows 7, Windows 8 or Windows 8.1 click a right mouse button and select Run as administrator in context menu.

Sentinel RTE Installer windows will be opened in several seconds:

At the end of installation Operation successfully completed message will be shown:

Please, press OK button in this message to finish RTE installation/reinstallation. Then web-browser page with RTE version will be opened to confirm successful installation:

NOTE! Finally, don't forget to add process hasplms.exe and port 1947 as exception in antivirus and firewall and connect usb-keys HASP.

[1] <http://sd.ascon.ru/ftp/Public/Utils/HASP%20SRM/foreign/haspdinst.zip>

[2] [http://sd.ascon.ru/ftp/Public/Utils/HASP%20SRM/driver/cmd/HASP\\_install.zip](http://sd.ascon.ru/ftp/Public/Utils/HASP%20SRM/driver/cmd/HASP_install.zip)