

Activation of the KOMPAS-3D trial[.]

10/28/2024 14:19:28

FAQ Article Print

Category:	FAQ in English::KOMPAS-3D FAQ	Last update:	10/24/2024 15:10:01
State:	public (all)		

Problem (public)

Activation of the KOMPAS-3D trial license starting from version v22

Solution (public)

PLEASE NOTE: The trial license does not work in a virtual machine and over remote access using the RDP protocol. To connect remotely to a PC where the trial version is installed, use the VNC protocol.

KOMPAS-3D must be installed before the activation of the evaluation license begins.

Run the activation v4 utility, this can be done from KOMPAS-3D (Menu: Help > The security key utility...)

1. Activation via the Internet.
2. Activation of the trial license on a PC without an Internet connection.

1. Activation via the Internet

In the activation utility, select the TRIAL LICENSE menu and click on the KOMPAS-3D Trial Mode button (click to get a license)

Enter your email address and click Activate.

Restart KOMPAS-3D.

2.Activation of the trial license on a PC without an Internet connection.

Algorithm:

- 1) Create a request file on a PC without an Internet connection
- 2) On a PC connected to the Internet, using the request file, create a license file.
- 3) Apply the license file to a PC without an Internet connection.

In the activation utility, select the TRIAL LICENSE menu and click the Offline Activation button

In the list of available Trial Licenses, select the required trial license and in the window that appears, specify the path to save the request file. Copy the received request file to a PC with an Internet connection

On a PC with an Internet connection.

In the activation utility, select the TRIAL LICENSE menu, click the Offline Activation button and then Activate .tralrequest

Specify the email address, click Activate, and in the window that appears, specify the path to save the license file. Copy the license file to a PC without an Internet connection.

On a PC without an Internet connection.

In the activation utility, select the TRIAL LICENSE menu, click the Offline Activation button and then the Apply button.triallicense. and in the window that appears, specify the path to the license file.