

KOMPAS-3D on network keys: clie[...]

06/04/2020 00:08:58

[FAQ Article Print](#)**Category:** FAQ in English::Software Protection::HASP4**State:** public (all)**Last update:** 12/16/2015 16:31:34

Keywords

nethasp.ini

Problem (public)

KOMPAS-3D on network keys: client configuration

Solution (public)

If you use KOMPAS-3D network licenses, you are to configure your application on each client computer.

To do it, please, replace <KOMPAS-3D installation directory>/Bin/nethasp.ini file with the one in attachment of this article, and then replace ServerName in it with you license server name or IP-address.

IMPORTANT: Don't remove empty lines at the end!